


Software Update Process


Software update will be notified on home screen with a red label on the “Settings” icon.



To start the update process, select « Settings » item from home screen,  , then select “Download” item, and follow instructions

You must have a data connection to download and install the software update. Because of the size of this update (about 1GB), we recommend that you use the Wi-Fi network for downloading.

Smartvision regularly checks the availability of updates and you will be notified automatically.

However, you can manually check for an update from "Settings"  , then select « About phone” , and finally select “System update”.

System:

- Accessibility :

- Add a shortcut to enable / disable the accessibility mode on Power management menu (long press on Power button).
- Add android buttons shortcut by using physical keypad :
 - Long press on “up arrow” key replaces the android tactile button “Menu”.
 - Long press on “down arrow” key replaces the android tactile button “Home”.
 - Long press on « C » key replaces the android tactile button “Back”.
- Command mode : add shortcut with keys combination:

This mode allows a quick access using the combination of a long press on the “#” key followed by a short press on numerical keys, 1,2,3 etc . To reach the shortcut action, press the numerical key before the 10 seconds timer after long pressing the “#” key. A beep is played after the long press on the “#” to validate the activation of the “command mode” and another “bip” is played if there is not action within 10 seconds to indicate the exit of the “command mode”.

- Long press « # » following by « 1 » reads the Smartvision status (Time , battery level, network...)
- Long press « # » following by « 2 » reads the screen contain
- Long press « # » following by « 3 » open the notification window
- Long press « # » following by « up » launches a cursor left moving

(Text editor or tabulation)

- Long press « # » following by « down » launches a cursor right moving (Text editor or tabulation)
- Long press « # » following by « Volume up » button increase ringtone sound level.
- Long press « # » following by « Volume down » button decrease ringtone sound level.

- Warning: Modification of the “Explore By Touch” behavior.

The “explore by touch” behavior has been modified to be safer and easier to use.

- Activation through the touch screen has been modified to avoid mistake. Now you can explore the screen by moving your finger on the screen, then the text-to-speech will vocalize each item pointed by your finger. No risk to launch or activate by mistake the item, since you have to validate by the “OK” key each action keeping your finger on the screen.
- Double tap to launch item has been removed, replacing by pushing “OK” key when your finger points an item on the screen.
- “Swipe” to reach the next item has been replaced : now an up or down swipe scrolls through the list screen by screen (it is used to reach the end of the list quicker for example).

- **User interface :**

- To get a better contrast for low vision end users, screen background is now black with white text. An option from “setting / accessibility / background color” allows the end user to define white or black user interface. Please note that the complete Android OS will be reloaded in case of change.
- Use numerical keypad (key 2 to 9) to reach faster a contact or an application by using the first letter. For example, press key “6 MNO” to reach “Magnifier” from applications list. Use also respectively “*” and “#” keys to reach the first and the last item of the list.
- User interface is faster.
- A bigger font has been added for test.
- Widget screen has been removed.

- **Text-To-Speech (TTS) :**

- Direct sound level management for the Text-To-Speech by using volume up and down keys. Ringtone output level is now accessible by using command mode (long press on # key) following by volume up and down keys.
- Screen reader and text-to-speech (TTS) improvement.
- “Editor Area” is now announced when selected.

Applications:

- **Phone :**
 - o Short press on “Voice Command” button during a call will activate or deactivate the Hand free mode.
 - o Through historical call list, incoming, outgoing or missed calls status is now announced.
- **Kapten - GPS - Navigation:**
 - o « map discovery » : vocalization has been improved/
 - o Issue about vocalization of the road name from the keyboard is resolved
- **Message :**
 - o Translation bug fixed in French and Dutch.
 - o Bug fix about “send message” answer, YES or No is now available bu using voice command.
 - o Bug fix to resolve when sending a long SMS, more than 1 screen size.
 - o Message status (read or unread) is now vocalized.
- **Contact :**
 - o To avoid problems related to specific format of contacts stored on the SIM card (unable to add fields, double display in case of import), now Contacts stored on the SIM card are not displayed. To view, modify and use contacts from SIM card, it is necessary to import them previously into the internal memory of SmartVision (see "Contact", "Menu", "Import / Export").

Restrictions:

- No

Note:

- For more information about new functionalities of this update please refer to the user manual, available through: <http://www.kapsys.com/fr/en/support/>